

Avaya Solution & Interoperability Test Lab

Application Notes for InfoTalk-Recognizer 10.0 with Avaya Aura® Experience Portal 7.0, Avaya Aura® Communication Manager 6.2 FP4 and Avaya Aura® Session Manager 6.2 FP4 – Issue 1.0

Abstract

These Application Notes describe the configuration steps required for InfoTalk-Recognizer 10.0 to successfully interoperate with Avaya Aura® Experience Portal 7.0, Avaya Aura® Communication Manager 6.2 FP4 and Avaya Aura® Session Manager 6.2 FP4. Avaya Aura® Experience Portal running VoiceXML applications hosted on Microsoft IIS utilizes the automatic speech recognition (ASR) features of InfoTalk-Recognizer 10.0 using the Media Resource Control Protocol (MRCP) Version 2.

Readers should pay attention to Section 2, in particular the scope of testing as outlined in Section 2.1 as well as the observations noted in Section 2.2, to ensure that their own use cases are adequately covered by this scope and results.

Information in these Application Notes has been obtained through DevConnect compliance testing and additional technical discussions. Testing was conducted via the DevConnect Program at the Avaya Solution and Interoperability Test Lab.

1. Introduction

These Application Notes describe the configuration steps required for InfoTalk-Recognizer 10.0 to successfully interoperate with Avaya Aura® Experience Portal 7.0, Avaya Aura® Communication Manager 6.2 FP4 and Avaya Aura® Session Manager 6.2 FP4. Avaya Aura® Experience Portal (AAEP) running VoiceXML applications hosted on Microsoft IIS utilizes the automatic speech recognition (ASR) features of InfoTalk-Recognizer 10.0 using the Media Resource Control Protocol (MRCP) Version 2.

InfoTalk-Recognizer is a software solution running both the InfoTalk-Recognizer ASR engine and the InfoTalk MRCP Server Version 2.0 application on Ubuntu 14.10.

2. General Test Approach

The general test approach is to place calls manually to Avaya Aura® Experience Portal running VXML applications that uses the ASR resources of InfoTalk-Recognizer solution.

DevConnect Compliance Testing is conducted jointly by Avaya and DevConnect members. The jointly-defined test plan focuses on exercising APIs and/or standards-based interfaces pertinent to the interoperability of the tested products and their functionalities. DevConnect Compliance Testing is not intended to substitute full product performance or feature testing performed by DevConnect members, nor is it to be construed as an endorsement by Avaya of the suitability or completeness of a DevConnect member's solution.

2.1. Interoperability Compliance Testing

This Interoperability Compliance Test included feature and serviceability testing. The feature testing focused on placing calls to Avaya Aura® Experience Portal that ran Voice XML scripts in English, Cantonese and Putonghua (Traditional Chinese) that uses the ASR engines on the InfoTalk-Recognizer solution. The compliance test focused on placing calls to verify the accuracy of ASR detection.

The serviceability testing focused on verifying the ability of InfoTalk-Recognizer solution to recover from adverse conditions such as rebooting of InfoTalk server and Avaya Aura® Experience Portal and disconnecting the LAN cables to the InfoTalk server.

2.2. Test Results

All test cases passed. Avaya Aura® Experience Portal 7.0 was successful in running applications that use the ASR resources of the InfoTalk-Recognizer solution. A point to note is that InfoTalk-Recognizer does not support built-in grammar for DTMF recognition.

2.3. Support

For technical support on InfoTalk-Recognizer and MRCP Server contact:

Telephone: +852 2190 9600
 Fax: +852 2788 2306

• Email: support@infotalkcorp.com

3. Reference Configuration

Figure 1 illustrates the configuration used to verify InfoTalk-Recognizer 10.0 solution. The InfoTalk-Recognizer 10.0 and InfoTalk MRCP Server 2.0 software were installed on Ubuntu 14.10. VoiceXML scripts that used the ASR engine were hosted on another Windows 2003 Server with Service Pack 2 installed running IIS 7.0. Avaya Aura® Experience Portal is connected to Avaya Aura® Session Manager and Avaya Aura® Communication Manager using SIP VoIP Connections. Avaya IP telephones were used to place calls to Avaya Aura® Experience Portal, which would run the VoiceXML applications. The applications would use the InfoTalk-Recognizer ASR engine for speech detection.




Figure 1: InfoTalk-Recognizer 10.0 with Avaya Aura® Experience Portal Configuration

4. Equipment and Software Validated

The following equipment and software were used for the sample configuration provided:

Equipment	Software	
Avaya Aura® Communication Manager on Avaya S8800	6.3.9	
Server (Duplex)	(Build R016x.03.0.124.0-21971)	
Avaya G450 Media Gateway	36.7.0	
Avaya Aura® System Manager on HP DL360 G7	6.3.11.8.2933	
Avaya Aura® Session Manager on Avaya S8800 Server	6.3.11.0.631103	
Avaya Aura® Experience Portal 7.0 running on VMware	EPM - 7.0.0.0.6604	
5.1u1	MPP - 7.0.0.0.6619	
Avaya 4548GT-PWR Ethernet Routing Switch	FW: 5.3.0.3	
Avaya 454601-F WK Emerilet Routing Switch	SW: v5.6.1.052	
Microsoft IIS on Windows Server 2003 Standard Edition	7.0	
SP2		
InfoTalk-Recognizer on Ubuntu 14.10 running on VMware	10.0	
4.1u1		

5. Configure Avaya Aura® Communication Manager

The configuration of the SIP Trunks between Communication Manager and Session Manager, and the routing of calls to Experience Portal are assumed to be in place and will not be discussed here. This section provides the additional procedures to configure Communication Manager for the purpose of administering InfoTalk-Recognizer. The configuration is performed via the System Access Terminal (SAT).

Description							
Enter the change	e ip-codec-set n	command	where n is a	a valid IP cod	dec-set ass	ociated	with
the IP network re	egion that is use	d by Expe	rience Portal	, typically th	e IP netwo	rk regio	n
assigned to the S	ession Manager	SIP Trun	k signaling g	group. Set Au	idio Code	c to an	
appropriate value	e supported by A	Avaya Aur	a® Experien	ice Portal and	d InfoTalk	-Recogn	izer.
_ * * *		•	-			C	
	,						
change ip-codec	-set 6				Page	1 of	2
	TD	Codoa Sot					
	IF	codec set					
Codec Set:	6						
Audio	Silence	Frames	Packet				
Codec							
	n	2	20				
3:							
4:							
5:							
	Enter the change the IP network reassigned to the Sappropriate value In this configura change ip-codec Codec Set: Audio Codec 1: G.711MU 2: 3: 4:	Enter the change ip-codec-set not the IP network region that is use assigned to the Session Manager appropriate value supported by A In this configuration, the G.711 Change ip-codec-set 6 IP Codec Set: 6 IP	Enter the change ip-codec-set n command the IP network region that is used by Experimental assigned to the Session Manager SIP Trunk appropriate value supported by Avaya Aur In this configuration, the G.711MU codec change ip-codec-set 6 IP Codec Set: Codec Set: 6 Audio Silence Frames Codec Suppression Per Pkt 1: G.711MU n 2 2: 3: 4: 5: 6:	Enter the change ip-codec-set n command where n is a the IP network region that is used by Experience Portal assigned to the Session Manager SIP Trunk signaling g appropriate value supported by Avaya Aura® Experient In this configuration, the G.711MU codec was used. Change ip-codec-set 6 IP Codec Set Codec Set: 6 Audio Silence Frames Packet Codec Suppression Per Pkt Size (ms) 1: G.711MU n 2 20 2: 3: 4: 5: 6:	Enter the change ip-codec-set n command where n is a valid IP code the IP network region that is used by Experience Portal, typically the assigned to the Session Manager SIP Trunk signaling group. Set Autappropriate value supported by Avaya Aura® Experience Portal and In this configuration, the G.711MU codec was used. Change ip-codec-set 6 IP Codec Set Codec Set: 6 Audio Silence Frames Packet Codec Suppression Per Pkt Size (ms) 1: G.711MU n 2 20 2: 3: 4: 5: 6:	Enter the change ip-codec-set n command where n is a valid IP codec-set ass the IP network region that is used by Experience Portal, typically the IP network assigned to the Session Manager SIP Trunk signaling group. Set Audio Code appropriate value supported by Avaya Aura® Experience Portal and InfoTalk. In this configuration, the G.711MU codec was used. Change ip-codec-set 6 Page IP Codec Set Codec Set: 6 Audio Silence Frames Packet Codec Suppression Per Pkt Size(ms) 1: G.711MU n 2 20 2: 3: 4: 5: 6:	Enter the change ip-codec-set n command where n is a valid IP codec-set associated the IP network region that is used by Experience Portal, typically the IP network region assigned to the Session Manager SIP Trunk signaling group. Set Audio Codec to an appropriate value supported by Avaya Aura® Experience Portal and InfoTalk-Recogn In this configuration, the G.711MU codec was used. Change ip-codec-set 6 Page 1 of IP Codec Set Codec Set: 6 Audio Silence Frames Packet Codec Suppression Per Pkt Size (ms) 1: G.711MU n 2 20 2: 3: 4: 5: 6:

6. Configure Avaya Aura® Experience Portal

The initial administration of Avaya Aura® Experience Portal and the configuration of the SIP VoIP Connection to Session Manager are assumed to be in place and will not be discussed here. This section covers the additional procedures of Avaya Aura® Experience Portal that is required for the purpose of administering InfoTalk-Recognizer. The following steps will be covered:


- Configuring the VoIP audio format
- Adding InfoTalk-Recognizer as a ASR server

Legal Notice © 2018 Aveys Inc. All Sights Reserved.


Adding applications

While reasonable efforts have been made to ensure that the information in this document is complete and accurate at the time of printing, Awaya assumes no liability for any errors. Awaya reserves

2. To configure the codec used by the Media Processing Platform (MPP) server, click **System**Configuration → MPP Servers in the left pane and click VoIP Settings.



3. Set **MPP Native Format** to **audio/basic** to configure the MPP server for G.711 mu-law to match the configuration on Communication Manager in **Section 5**. Scroll down the page and click **Save**.




4. InfoTalk-Recognizer is not natively included in the set of ASR engines supported by Avaya Aura® Experience Portal and will not initially appear in the ASR configuration screen. To add InfoTalk-Recognizer to the list of supported engines, log into the EPM server, either locally or remotely through Secure Shell (SSH), and locate the languages.properties file found in /opt/Tomcat/apache-tomcat-6.0.32/webapps/VoicePortal/WEB-INF/classes/messages/. Edit the file and add the lines shown below to the appropriate section.


```
< Some lines removed for brevity >
#{{START:PROPERTIES:EXPERIENCEPORTAL 7.0
# THIS SECTION IS SPECIFIC TO EXPERIENCE 7.0
# 1. ADD ANY NEW PROPERTIES FOR EXPERIENCE 7.0 TO ADDITIONS SECTION WITHIN 7.0
SECTION.
# 2. TO MODIFY A PRE-EXISTING PROPERTY, MOVE IT TO MODIFICATIONS SECTION WITHIN 7.0
AND THEN MODIFY IT.
# 3. TO DELETE A PRE-EXISTING PROPERTY, MOVE IT TO DELETIONS SECTION WITHIN 7.0 AND
THEN COMMENT IT OUT.
#{{START:PROPERTIES:EXPERIENCEPORTAL 7.0:ADDITIONS
# Specify any new properties for Experience Portal 7.0 here.
InfoTalkMRCPLabels=MRCP V1, MRCP V2
InfoTalkTransportLabels=TCP
< remaining lines removed for brevity >
```

5. Locate the languages.properties file found in /opt/Tomcat/apache-tomcat6.0.32/webapps/voicePortal/WEB-INF/classes/config. Edit the file and add the fields and lines


```
shown below to the appropriate section.
# Engine Type options displayed on the page
asrEngines=SinoVoice, InfoTalk, IBM WVS, Loquendo, Nuance
ttsEngines=SinoVoice, InfoTalk, IBM WVS, Loquendo, Nuance
asrEnginesAmsOnly=Nuance
ttsEnginesAmsOnly=Nuance
# Engine Type conversion from display to internal data in the databas
< Some lines removed for brevity >
InfoTalkASR=infotalk asr
# Engine Type conversion from internal data in the database to display
< Some lines removed for brevity >
infotalkasr=InfoTalk
# Languages
< Some lines removed for brevity >
InfoTalkASRlanguages=zh-HK ITCan F,zh-TW ITPut F,en-US ENG1 F
# Language Default
< Some lines removed for brevity >
InfoTalkASRlanguagesDefault=en-US
# default base port
< Some lines removed for brevity >
InfoTalkBasePort=554
# default New Connection per Session
< Some lines removed for brevity >
InfoTalkPerPort=Yes
# default URL
< Some lines removed for brevity >
InfoTalkRtspUrlAsr=/media/ASR
# Grammar Type
< Some lines removed for brevity >
infotalkGrammarType=srgs
```



- 6. Reboot the EPM server for the above changes to take effect.
- 7. To configure the InfoTalk-Recognizer server, click **System Configuration** → **Speech Servers**. Click the **ASR** tab and click **Add**.




8. In the **Add ASR Server** page, select **InfoTalk** as the **Engine Type**. This engine type option was added by modifying the languages.properties files in **Steps 4** and **5**. In the **MRCP** section, set **Protocol** to **MRCP V2**. Specify the **Name**, select **Yes** to **Enable**, set **Network Address** to the IP address or Full FQDN of the InfoTalk-Recognizer Server and select the desired **Languages** used by the applications. The **Total Number of Licensed ASR Resources** should also be set to the number of licenses available on the InfoTalk-Recognizer Server. All other fields were left at their default values. Click **Save**.



9. To assign InfoTalk-Recognizer to an Avaya Aura® Experience Portal application, click System Configuration → Applications and then click Add on the Applications page (not shown). Configure the Add Application page as shown below. This configuration assigns the default Avaya Aura® Experience Portal test application deployed on the http server to the called number 10392. Specify the Name, select Yes to Enable, set MIME Type to VoiceXML and set VoiceXML URL to HTTP server address location of the VoiceXML script. Select InfoTalk for ASR and then select the appropriate Languages to use. Ensure that the Advanced Parameters for Support Remote DTMF Processing is set to No as InfoTalk-Recognizer does not perform DTMF processing. Click Save (not shown).

Repeat this procedure to assign InfoTalk-Recognizer to other Experience Portal applications.



7. Configure InfoTalk-Recognizer and InfoTalk MRCP Server

InfoTalk-Recognizer and InfoTalk MRCP Server were installed on a HP server with Intel Xeon X5670, 2.9 GHz with 8 GB of memory running Ubuntu 14.10. As all communication between the InfoTalk server and Avaya Aura® Experience Portal is via TCP/IP, it is strongly suggested that both systems be placed on the same IP subnet with minimal network traffic in order to minimize network latency.

The sections that follow detail the InfoTalk-Recognizer setup:

- Install software
- Install License
- Start up InfoTalk MRCP server

7.1. Install software

Step	Description
	Installing InfoTalk-Recognizer & MRCP software
1.	The InfoTalk-Recognizer software is distributed on a DVD-ROM. To install, place the DVD-
	ROM into the drive. The installation runs through the following steps:
	1. Mount the DVD ROM.
	2. Login as root.
	3. Install the InfoTalk-Recognizer software by executing the command:
	dpkg -i <dvd_mount_point>/infotalk.deb</dvd_mount_point>
	4. InfoTalk MRCP server and Recognizer will be started automatically as a service.
	5. The service name is " infotalk " and the working directory is at /var/lib/infotalk.

Step | **Description Configuring InfoTalk-MRCP Server software** Modify the file MRCPServer.cfg found at /opt/Infotalk/mrcp/MRCPServer.cfg. The line shown below determines the location of the configuration file for the InfoTalk-Recognizer ASR engine. asr_config_file=/opt/Infotalk/mrcp/asr.cfg The line below determines the maximum instances of the ASR engine. The value must correspond to the number of licenses purchased for InfoTalk-Recognizer. max_session= 10 server port = 5060 mrcpv2 port = 1554 log level= 5 max session= 10 mrcp version= 2 **TCP** sip protocol= log dir= ./log /opt/Infotalk/mrcp/asr.cfg asr config file= /opt/Infotalk/mrcp/tts.cfg tts config file= tts enable= 1 tts service name= TTS msg codec= UTF-8 tts default lang= en-us asr unicode result= 1 Modify the file **asr.cfg** found at **/opt/Infotalk/mrcp/**. Locate lines shown below. The variable **client_server** should be set to 0. The MRCP Server will load the Recognizer engine internally. [rec-client]

 $client_server = 0$

7.2. Install License

After installing the SDK, the next step is to install the license file.

Step	Description
	Installing InfoTalk License Server
1.	Install InfoTalk License following the instructions below:
	1. Connect the dongle to the USB port.
	2. Login as root.
	3. Use the cd command to move to the license directory in the SDK DVD.
	4. Run the Install_INFOTALK script and follow the directions to install and configure the InfoTalk Software License Manager.
	5. Copy the software license file accompanying the dongle to the directory. /opt/Infotalk/license/
	Verify the licenses installed
2.	Open the license server log file at /opt/Infotalk/license/license.log and check all the license features installed. e.g.
	13:19:19 (infotalk) TTSEng1 TTSEng TTSMan 13:19:19 (infotalk) TTSPut TTSCan GDLTool 13:19:19 (infotalk) GDLC AsrClient VoiceTouch 13:19:19 (lmgrd) infotalk using TCP-port 4122
3.	Open the software license file using any text editor and check the number of licenses available e.g.
	FEATURE VoiceTouch infotalk 1.0 permanent 10
	which means it support 10 instances of "VoiceTouch" - InfoTalk-Recognizer

7.3. Start Up InfoTalk MRCP Server

Console Mode:


Step	Description
	Start up InfoTalk MRCP Server – Console Mode
1.	Run the script file "start_mrcp_server.sh" at /opt/Infotalk/mrcp/ to start up the InfoTalk MRCP Server.

Service Mode:


Step	Description
	Start up InfoTalk MRCP Server – Service Mode
1.	Run the command "service infotalk start" to start the InfoTalk MRCP Server.

8. Verification Steps


This section provides the verification steps that may be performed to verify that Avaya Aura® Experience Portal can run VoiceXML applications that use the InfoTalk-Recognizer for ASR speech detection.



2. From the EPM web interface, click **Real-time Monitoring** → **Port Distribution** on the left pane. On the **Port Distribution** page, click the specific MPP server on the right pane (not shown) and click **OK**. The screen below will be shown. Click on the number below the **Port** column and a pop-up window will show the **Port Information**. Verify that the **State** of the ports under **Status** on the MPP server is **In service**.



3. Place some calls to Avaya Aura® Experience Portal running a VoiceXML script which uses the InfoTalk-Recognizer for speech detection. Verify that the application answers the calls and that the application is able to announce the ASR synthesized prompts to the caller. From the Avaya Aura® Experience Portal web interface, click **Real-time**Monitoring → Active Calls on the left pane and verify that the ASR Server in use is InfoTalkASR.



9. Conclusion

These Application Notes describe the compliance-tested configuration used to validate Avaya Aura® Experience Portal 7.0 with InfoTalk-Recognizer 10.0 and InfoTalk MRCP Server 2.0. All test cases were completed successfully with a note indicated in **Section 2.2.**

10. Additional References

The following documents are available at http://support.avaya.com.

- [1] Administering Avaya Aura® Communication Manager, Release 6.3, Issue 10, June 2014, Document ID 03-300509.
- [2] Administering Avaya Aura® Experience Portal, Release 7.0, Issue 1, Dec 2013.

The following documents are available from InfoTalk:

[3] InfoTalk-Recognizer Service Developer's Guide, Version 9.0

©2015 Avaya Inc. All Rights Reserved.

Avaya and the Avaya Logo are trademarks of Avaya Inc. All trademarks identified by ® and TM are registered trademarks or trademarks, respectively, of Avaya Inc. All other trademarks are the property of their respective owners. The information provided in these Application Notes is subject to change without notice. The configurations, technical data, and recommendations provided in these Application Notes are believed to be accurate and dependable, but are presented without express or implied warranty. Users are responsible for their application of any products specified in these Application Notes.

Please e-mail any questions or comments pertaining to these Application Notes along with the full title name and filename, located in the lower right corner, directly to the Avaya DevConnect Program at devconnect@avaya.com.